

# Extended Collection Properties

The Extended Collection properties will show you what characteristics will be used for each collection and when all or multiple collections are selected in the LUNA Viewer.

Watch the video:

## Site level characteristics

Site level characteristics are identified in the column called Collection where the values are (-1) and (All Collections). This is where you can edit the Collection Description, Theme (default, blue or white), Header Graphic and the Default Group you see on the Luna Viewer when you have more than one collection selected or are looking at all collections.

Under the more tab, you will find Extended Collection Properties

The screenshot shows the 'more' dropdown menu with the following options: IP Ranges and Extended Collection Properties. Below the menu is a table with the following data:

Collection	Collection Description	Home Graphic URL	Header Graphic URL	Default Media Group ID
(-1)			/luna/images/luna-default-header.jpg	0
(All Collections)	This is a description of all the collections I have. This is the description you will see in the Viewer when looking at All Collections (no collection selected yet). This is where you can change the description if you like.		/luna/images/luna-default-header.jpg	0
collection 1 (SamsTest~1~1)	sams test 1			0
Dryden Historical Images (NVA2~74~74)	Airplanes and rockets! Ohhh my!		http://192.168.21.182:8181/graphics/luna-default-header.jpg	0
Earth Observatory Collection (nasaNAS~10~10)	Planets and stars!		http://192.168.21.182:8181/graphics/luna-default-header.jpg	0
samslib (samsam~1~1)	sams brief desc		http://192.168.21.182:8181/graphics/luna-default-header.jpg	0

Showing 1 to 6 of 6 entries

Click on one of the two entries you will need to edit (-1) and (All Collections) then choose the Edit Selected button.

**-1** ✕

Collection Description

All Collections Description


Header Graphic URL


Default?

Default Group ID

Theme

Here you can Change the Collection Description, Header Graphic URL Default group to load in the Featured Media and the theme.

 For the Header Graphic, copy the URL from the Collection Manager and paste it here.

 For the theme type in one of the following default, blue or white

To make these changes take affect you will need to you will need to do a Soft Reset under the more tab. If you don't have the Soft Reset option. Talk to your LUNA administrator and ask them to do it.