

# LUNA 7.5.2.7, 7.5.2.6, 7.5.2.5, 7.5.2.3 & 7.5.2.2 Patch Release Notes

Posted Mar. 9, 2022

The LUNA 7.5.2.7 patch release fixes the following bug:

- Fixed a bug in the installer that occasionally caused content not to load in the LUNAversal Viewer.

Posted Jan. 19, 2022

The LUNA 7.5.2.6 patch release fixes the following bug:

- Updated LUNA's Java-based logging package to Log4j2 due to a very serious vulnerability that was publicly reported. The previous version of LUNA used Log4j version 1 which did not contain the serious vulnerability, but prompted us to update to a fully secure version of log4j version 2.

Posted Nov. 30, 2021

The LUNA 7.5.2.5 patch release fixes the following bugs:

- Fixed a bug causing issues with playable media working in both the Viewer and Library, whereby the movies and audio don't display when the button to view the media in a popped out window is clicked.
- Fixed a bug in the Library causing the Record ID to be missing from the export.

Posted Oct. 13, 2021

The LUNA 7.5.2.3 patch release fixes the following bugs:

- Fixed a bug in Viewer causing narrow vertical images to load at a lower resolution than they should in the Mirador viewer.
- Fixed a bug whereby making a theme change in the Viewer broke some media icons in the Library.

Posted Sep. 22, 2021

The LUNA 7.5.2.2 patch release fixes the following bugs:

- Fixed a bug causing problems when more than 2 zipped book files were uploaded to LUNA, whereby only the first and last book file would load into the system.
- Fixed a bug whereby the Quickview bar does not display in the Viewer's Detail View when the Title contains a # sign.